

1. CITP protocol suite specification

2007-09-16 Revised documentation into a single document.

1.1 History

2007-09-28	Added first comments for MSEX revision, highlighted in red.	
2008-01-25	Cleaned up MSEX 1.1 changes for element libraries.	
2008-05-28	Minor corrections and clarifications in MSEX.	
2008-08-21	Completed MSEX element types 4 - 8, accompanied by the Generic Element Information packet	
2008-10-11	Added BSR E1.31 to the DMX connection strings table.	
2008-11-08	Added first OMEX packet suggestions.	
2009-02-14	OMEX packet suggestion update and general revision of the introduction section.	
2009-02-18	22-18 Removed deprecation note of PINF/PNam as it does have its use (with clarifying comments).	
2009-05-17	Added note regarding problems with MSEX/GLEI message.	
2009-06-23	Clarified the note regarding contiguous element identifiers.	
2009-11-27	Added first draft of MSEX 1.2 extensions.	
2010-06-12	MSEX 1.2 finalized.	
2010-08-29	Clarified the role of the PNam message.	
2011-07-20	Added FINF SPos and Posi message suggestions.	
2012-05-02	Clarified MSEX image formats.	
2012-07-25	Corrected MSEX ELTh and EThn ThumbnailBuffer type missing []. Minor style fixes.	
2012-08-20	Added new 3D mesh MSEX element type and fixed minor typos.	

1.2 Introduction

The CITP (Controller Interface Transport Protocol) is a dual layer protocol suite that has been designed for communication between lighting consoles, media servers and visualizers. This document describes how it is used on top of an IP stack, but the packets could easily be used over other media as well, such as USB links.

The top layer, CITP, consists of a single message header with content information and support for fragmentation and stream synchronization. This message header is used in the beginning of all CITP protocol suite packets.

The second layer of CITP consists of the PINF, SDMX, FPTC, FSEL, FINF, MSEX and OMEX protocols. Each of these have been designed for a specific purpose, but some of them are closely related (such as FPTC, FSEL and FINF that all operate on a given set of lighting fixtures). Any manufacturer can extend the CITP protocol at the second layer level using a non-reserved layer identifier.

1.3 Lighting console behaviour

Datagram (UDP) socket, port 4809, joined to multicast address 224.0.0.180:

- Regularly send a CITP/PINF/PLoc message with no listening port.
- Receive CITP/PINF/PLoc messages to be aware of available visualizers and media servers.
- Connect either automatically or on user demand to an available visualizer and/or media server.
- Receive CITP/MSEX/StFr Stream Frame video content from media server video subscriptions.

For all TCP connections to a media server:

- Send CITP/PINF/PNam message immediately after connecting.
- Send CITP/MSEX/CInf Client Information message immediately after connecting.
- Receive CITP/MSEX/SInf Server Information and CITP/MSEX/LSta layer status messages.

- Send CITP/MSEX/GELI Get Element Library Information message(s) and initiate element library update. Request all libraries of relevant type to the media server in question (as identified by the CITP/PINF/PLoc Name field).
- Send CITP/MSEX/GVsr Get Video Sources message to retrieve information about available video feeds.

For all TCP connections to a visualizer:

- Send CITP/PINF/PNam message immediately after connecting.
- Send a CITP/SDMX/UNam Universe Name for each DMX universe controlled to provide display names.
- Either Send CITP/SDMX/ChBk Channel Block messages with DMX data,
- or Send a CITP/SDMX/SXSr Set External Source message to specify an alternative DMX transfer method.
- Receive CITP/SDMX/ChBk messages for "autofocus" purposes.
- Send and receive CITP/FPTC, CITP/FSEL and CITP/FINF messages when fit.

1.4 Media server behaviour

TCP listening socket on any (known) port:

- Accept incoming connections from any lighting console or visualizer. If the media server can only handle a limited number of simultaneous connections then it should actively refuse any further connection attempts.

Datagram (UDP) socket, port 4809, joined to multicast address 224.0.0.180:

- Regularly send a CITP/PINF/PLoc message containing the port on which the listening socket is listening.

For all accepted incoming TCP connections from a lighting console or visualizer: Mbox does not send PNam

- Send CITP/PINF/PNam message immediately after connecting.
- Send a CITP/MSEX/SInf Server Information message (MSEX 1.0 or MSEX 1.1).
- Receive CITP/MSEX/CInf Client Information message from lighting console and respond with a

CITP/MSEX/SInf Server Information message (MSEX 1.2 or later).

- Regularly send a CITP/MSEX/LSta Layer Status message.
- Receive and respond to CITP/MSEX element library browsing messages.
- Send CITP/MSEX element library information messages on library changes.
- Receive and respond to CITP/MSEX video stream browsing and subscription messages.

1.5 Visualizer behaviour

TCP listening socket on any (known) port:

- Accept incoming connections from any lighting console.

Datagram (UDP) socket, port 4809, joined to multicast address 224.0.0.180:

- Regularly send a CITP/PINF/PLoc message containing the port on which listening socket is listening.
- Receive CITP/PINF/PLoc message to be aware of available media servers.
- Connect either automatically or on user demand to an available media server.
- Receive CITP/MSEX/StFr Stream Frame video content from media server video subscriptions.

For all accepted incoming TCP connections from a lighting console:

- Send CITP/PINF/PNam message immediately after connecting.
- Receive CITP/SDMX/UNam Universe Name messages.
- Receive CITP/SDMX/ChBk messages with DMX data.
- Optionally support CITP/SDMX/SXSr messages and receive DMX data over other protocols.
- Send CITP/SDMX/ChBk messages for "autofocus" purposes.
- Send and receive CITP/FPTC, CITP/FSEL and CITP/FINF messages when fit.

For all TCP connections to a media server:

- Send CITP/PINF/PNam message immediately after connecting.
- Send CITP/MSEX/CInf Client Information message immediately after connecting.
- Receive CITP/MSEX/SInf Server Information and CITP/MSEX/LSta layer status messages.
- Send CITP/MSEX/GVSr Get Video Sources message to retrieve information about available video feeds.

1.6 Device status / Operations management servers

Work in progress.

1.7 General IP notes and hints

PC based applications must choose listening ports and set socket address reusability flags as necessary to avoid blocking eachother when run on the same network interface. Achieve this by calling listen() for port 0 and

retrieving the port chosen by the operating system with getsockname(), and by setting the SO_REUSEADDR (and possibly also SO_REUSEPORT) option on the multicast socket before joining the multicast address.

To join a multicast address, use setsockopt() with IPPROTO_IP and IP_ADD_MEMBERSHIP.

2. Definitions

These specifications target lighting software developers. It contains C style types and annotation, although mostly on a pseduo-code level.

2.1 Data types

All structures and variables of CITP use little endian byte order (least significant byte first, "PC standard") and 1-byte packing of C-structures.

Open arrays of ucs1 or ucs2 are null terminated strings.

2.2 Cookies

The Cookie (and ContentType) fields can be found in CITP headers in both layers. The constant values of these fields are documented using string notation, for instance "CITP" for the CITP header Cookie field. This should be interpreted as sending 'C','I','T','P' over the network.

2.3 DMX Connection Strings

Instead of defining constants and fixed field for various DMX source protocols, a connection string approach is used instead. The following table illustrates well-defined DMX connection strings in CITP:

Protocol	Format	Examples
ArtNet	"ArtNet/ <net>/<universe> /<channel>"</channel></universe></net>	"ArtNet/0/0/1" - The first channel of the first universe on the first network.
Avab IPX	"AvabIPX/ <net>/<universe> /<channel>"</channel></universe></net>	"AvabIPX/0/0/1" - The first channel of the first universe on the first network.
BSR E1.31	"BSRE1.31/ <universe>/<channel>"</channel></universe>	"BSRE1.31/0/1" - The first channel of the first universe.
ETC Net2	"ETCNet2/ <channel>"</channel>	"ETCNet2/1" - The first ETCNet2 channel.

3. CITP, base layer

The base layer as such does not define any packages, it merely adds a header that encapsulate all messages.

3.1 Header definitions

3.1.1 The CITP header

The CITP layer provides a standard, single, header used at the start of all CITP packets:

```
struct CITP_Header
{
                                    // Set to "CITP".
   11 i n + 32
            Cookie;
         VersionMajor;
   uint8
                                    // Set to 1.
   uint8
           VersionMinor;
                                    // Set to 0.
   union
                 RequestIndex; // See below InResponseTo; // See below
      uint16
     uint16
  // The size of the entire message, including
                                       (the name of the second layer).
};
```

RequestIndex/InResponseTo: These allow request/response message pairs to be better associated and is particularly useful for debugging purposes. A node that sends request messages (such as a Lighting Console requesting info from a Media Server) should maintain a request counter, and increment this with every request message sent. When the other side sends a response to a specific request message, it should set this field to the same value as was found in the corresponding request message. The value of 0 is taken to mean 'ignored', so proper RequestIndex values should start at 1 (and wrap back around to 1, avoiding the 0 'ignored' value). This was introduced for MSEX 1.2 and was previously a reserved 2-byte alignment field.

Note: Receipt of any unrecognised or unsupported messages must not be treated as an error condition.

4. CITP/PINF, Peer Information layer

The Peer Information layer is used to exchange peer information, both when connected and when locating peers on the network.

The PINF/PNam message was previousley broadcasted on UDP port 4810, but that behaviour has now been deprecated. Instead, the PINF/PLoc message is multicasted on address 224.0.0.180, port 4809. Do note that it is a good idea to send a PINF/PName message as a first over any established connection!

4.1 Header definitions

4.1.1 The PINF header

The PINF layer provides a standard, single, header used at the start of all PINF packets:

4.2 Message definitions

4.2.1 PINF / PNam - Peer Name message

The PeerName message provides the receiver with a display name of the peer. In early implementations of CITP, the PNam message was broadcasted as a means of locating peers - now the PLoc message is multicasted instead. The PNam message is still useful though, as a message transferred from a peer connected to a listening peer.

4.2.2 PINF / PLoc - Peer Location message

The PeerLocation message provides the receiver with connectivity information. If the ListeningTCPPort field is non-null, it may be possible to connect to the peer on that port using TCP. If the peer can only handle a limited number of simultaneous connections, then additional connections should be actively refused. The Type field instructs the receiver what kind of peer it is and the Name and State fields provide display name and information.

```
struct CITP_PINF_PLoc
   CITP_PINF_Header CITPPINFHeader;
                                          // The CITP PINF header. PINF ContentType is "PLoc".
   uint16
                      ListeningTCPPort:
                                          // The port on which the peer is listening for
                                             incoming TCP connections. 0 if not listening.
   ucs1
                                          // Can be "LightingConsole", "MediaServer",
                      Type[];
                                              "Visualizer" or "OperationHub".
   ucs1
                                          // The display name of the peer. Correspons to the
                      Name[];
                                             PINF/PNam/Name field.
   ucs1
                      State[];
                                          // The display state of the peer. This can be any
                                             descriptive string presentable to the user such
                                             as "Idle", "Running" etc.
};
```

5. CITP/SDMX, Send DMX layer

The SDMX layer is used to transmit DMX information. CITP supports transmitting a single - wide - universe of DMX channels with at most 65536 channels. It also supports designating an alternative DMX source such as ArtNet or ETCNet2 (see "connection strings" in the Definitions section).

5.1 Header definitions

5.1.1 The SDMX header

The SDMX layer provides a standard, single, header used at the start of all SDMX packets:

```
struct CITP_SDMX_Header
{
     CITP_Header CITPHeader; // CITP header. CITP ContentType is "SDMX".
     uint32 ContentType; // Cookie defining which SDMX message it is.
}:
```

5.2 Message definitions: Transfer of DMX channel levels

5.2.1 SDMX / EnId - Encryption Identifier message

The EncryptionIdentifier message is used to agree on encryption schemes when transferring DMX channels. The usage of this message depends completely on the peers communicating it; the contents and results of this message is not part of the CITP specification - it must be agreed upon a priori.

5.2.2 SDMX / UNam - Universe Name message

The Universe Name message can be sent by a DMX transmitting peer in order to provide the other end with a displayable name of a universe.

5.2.3 SDMX / ChBk - Channel Block message

The Channel Block message transmits raw DMX levels to the recipient. How to handle Blind DMX levels is up to the recipient, but the recommended procedure for a visualizer is to switch over to blind DMX whenever such is present and to revert back after some short timeout when it is no longer transmitted.

5.3 Message definitions: Alternate DMX source management

5.3.1 SDMX / SXSr - Set External Source message

The Set External Source message can be sent as an alternative to the ChBk message above, when DMX should be tapped from another protocol on the other end. In the event of handling multiple universes, the external source specified should be treated as the base universe of a consecutive series.

6. CITP/FPTC, Fixture patch layer

The Fixture Patch layer is used to communicate fixture existence and patch information. Fixtures are identified by 16-bit unsigned integeres with a range of valid values between 1 and 65535. In most consoles this value maps directly to a "Channel", "Unit" or "Device".

The FPTC layer is built on the following design decisions:

- Unpatched fixtures do not exist from the FPTC layers's point of view. When a fixture is unpatched using the UnPatch message, it is deleted and seizes to exist. However, the fixture may continue to live in the visualizer or the console, without association to a universe. Whenever the fixture is associated with a universe again, it is reintroduced through the Patch message.
- When a fixture is repatched (ie moved to another channel or universe) it does not pass through an unpatched state.
- In the visualizer, it may possible to change the mode of a fixture. Different modes for one fixture usually use different amounts of channels, however sometimes a different mode only changes the interpretation of one or more control channels. When a mode is changed in the visualizer, an unpatch message is not sent, only a new patch message. If the new mode consumes a different amount of channels, this can be told by the ChannelCount field of the patch message. If it does not, there is no way of telling.
- A fixture can change its patch and mode, but never its make or name. The visualizer attempts to map the fixture make and name against its library.
- Fixture identifiers must be persistent. When both the visualizer and the console have reloaded a pair of matching projects, the fixture identifiers must still be the same.
- When a project is closed on either side, fixtures are not unpatched. The same applies to when a universe in the visualizer is deleted or unassociated with a console.
- No synchronisation mechanism exists in CITP, which communicates project closing/opening information. This must be handled by the user by opening and closing matching projects simultaneously.
- When the visualizer or console takes automatic actions as a result of incoming patch messages, it must not result in an echo.

6.1 Header definitions

6.1.1 The FPTC header

The FPTC layer provides a standard, single, header used at the start of all FPTC packets:

6.2 Message definitions

6.2.1 FPTC / Ptch - Patch message

Patch messages are sent when fixtures are introduced or repatched. The patch message contains the identifier of the fixture added, the sender fixture (library) type make and name of the fixture added and the patching information..

```
struct CITP_FPTC_Ptch
   CITP_FPTC_Header CITPFPTCHeader;
                                          // The CITP FPTC header. FPTC ContentType
                                             is "Ptch".
                     FixtureIdentifier; // Fixture identifier.
   uint16
   uint8
                     Universe;
                                         // Patch universe (0-based).
   uint8
                    Reserved[1];
                                         // 4-byte alignment.
                    Channel:
                                         // Patch channel (0-based).
   uint16
                                         // Patch channel count (1-512).
   uint16
                    ChannelCount;
                                         // Fixture make (only null if omitted).
   ucs1
                     FixtureMake[];
                                         // Fixture name (never omitted).
   ucs1
                     FixtureName[];
};
```

6.2.2 FPTC / UPtc - Unpatch message

Unpatch messages are sent when fixtures are deleted or unpatched. The unpatch message only contains the identifiers of the fixtures removed. An empty fixture identifier array indicates complete unpatching.

6.2.3 FPTC / SPtc - SendPatch message

The SendPatch message instructs the receiver to send Patch messages in response, one for each fixture specified in the FixtureIdentifiers array. If no fixture identifiers are specified, the entire Patch should be transferred in response. This procedure can be used for testing the existence of fixtures on the remote side or to synchronize the entire patch information..

7. CITP/FSEL, Fixture Selection layer

The Fixture Selection layer is used to carry fixture selection information. Fixture identification is discussed in the CITP/FPTC section.

7.1 Header definitions

7.1.1 The FSEL header

The FSEL layer provides a standard, single, header used at the start of all FSEL packets:

7.2 Message definitions

7.2.1 FSEL / Sele - Select message

The Select message instructs the receive to select a number of fixtures. If the Complete field is non-zero, only the fixtures identified in the message should be selected and all others should be deselected, thus achieving a full synchronization.

7.2.2 FSEL / DeSe - Deselect message

The Deselect message acts similarly to the Select message. However, a Deselect message deselects the fixture specified, rather than selectin them. A Deselect with no fixture specified should deselect all fixtures.

8. CITP/FINF, Fixture Information layer

The Fixture Information layer is used to carry additional fixture information. Fixture identification is discussed in the CITP/FPTC.

8.1 Header definitions

8.1.1 The FINF header

The FINF layer provides a standard, single, header used at the start of all FINF packets:

8.2 Message definitions

8.2.1 FINF / SFra - Send Frames message

This messages informs the receiver to send frame messages for the specified fixtures.

8.2.2 FINF / Fram - Frames message

This messages informs the receiver about the filters & gobos of a fixture.

8.2.3 FINF / SPos - Send Position message PRELIMINARY

This message informs the receiver to send position messages for the specified fixtures.

8.2.4 FINF / Posi - Position message PRELIMINARY

This message informs the receiver about the position of the specified fixture(s). Coordinates are expressed in metres.

```
uint16 FixtureIdentifier;  // Fixture identifier.
float32 PositionX;  // Position X axis component.
float32 PositionY;  // Position Y axis component.
float32 PositionZ;  // Position Z axis component.
}[];
};
```

8.2.5 FINF / LSta - Live status message PRELIMINARY

This message can be sent in any direction on a regular basis. The flag mask and flag fields size is dynamic in order to allow future expansion without redifinition.

9. CITP/OMEX, Operations Management layer

PRELIMINARY

The Operations Management EXtensions layer is used for metadata communication.

9.1 Header definitions

The OMEX layer provides a standard, single, header used at the start of all OMEX packets:

9.2 Message definitions: DMX device status signalling

Status signalling of DMX devices is

9.2.1 OMEX / SDDS - Signal DMX Device Status

Sent to signal a status for one or more devices. A status is identified by a short string which is used again when clearing or updating the status (by sending a new SDDS message). It is typically a short string, such as "Offline", "On fire" or "Lamp fail".

```
struct CITP_OMEX_SDDS
    CITP_OMEX_Header CITPOMEXHeader; // CITP OMEX header. OMEX ContentType
                                                           is "SDDS".
                         StatusIdentifier[]; // Displayable status tag.
    ucs2
                        Severity; // 50 = Info, 100 = Warning, 150 = Error
Category[]; // Category identifier.
ShortText[]; // Short descriptive text.
LongText[]; // Long descriptive text.
    uint8
    ucs2
    ucs2
                                                     // Long descriptive text.
// The number of following device information
                         LongText[];
DeviceCount;
    ucs2
    uint16
                                                          blocks for which to set this status.
    struct DeviceInformation
         ucs1 DMXConnectionString; // A DMX connection string.
    };
};
```

9.2.2 OMEX / CDDS - Clear DMX Device Status

Sent to clear a specific status from a set of devices. It is not necessary that the status is cleared from all deviced that have it set, but it is possible. If a status clear is requested for a device that is not known to have status, the request is silently ignored.

10. CITP/MSEX, Media Server Extensions layer

The Media Server EXtensions layer is used for communication with Media Servers.

For information about how peers find eachother and connect, see the Connectivity section. Typically all packets are sent over a peer-to-peer TCP socket connection, except for the MSEX/StFr message which is sent over the multicast address for all to process.

MSEX Versions

Currently acknowledged versions of MSEX are 1.0, 1.1 and 1.2. During a session, the appropriate MSEX version that is common to both sides must be established and used for all communication - different versions cannot be mixed in a single session. See the MSEX/SInf and MSEX/CInf messages also regarding supported version signalling.

Prior to MSEX 1.2 it was expected that all client and server implementations check the MSEX version of all received messages to ensure that the message format is acceptable. Starting with MSEX 1.2 this is a mandatory requirement.

There is no requirement for an implementation of a specific MSEX version to support any previous MSEX versions, for this reason the version returned by the MSEX/SInf message must be used for all communication by both sides.

Establishing communications

Prior to MSEX 1.2, a media server was expected to send a MSEX/SInf Server Information message immediately after connecting to a lighting console or visualiser. This approach has the drawback that the MSEX/SInf message format has to be fixed since the media server is unaware of what MSEX version(s) the other side supports. Starting with MSEX 1.2, the lighting console or visualiser must send a MSEX/CInf Client Information message to the server immediately after connecting, and the server will respond with a version 1.2 or later MSEX/SInf message.

NB: Although the MSEX/Clnf message format must be fixed, provision has been made to allow extra data to be appended as a future-proofing measure.

Highest Common MSEX Version

For MSEX 1.2 and later, the server must establish the Highest Common MSEX Version when a MSEX/CInf is received from a newly connected lighting console or media server. This is the highest MSEX version that is supported on both sides, and must be used for all unsolicited messages, such as MSEX/SInf, MSEX/LSta and MSEX/ELUp. The Highest Common MSEX Version is at least 1.2.

Mandatory messages

Implementations can choose to implement a subset of MSEX messages to suit their needs, but some messages are essential for correct interoperation and are marked as mandatory. The mandatory messages are:

- 1. CInf Client Information message
- 2. SInf Server Information message
- 3. LSta Layer Status message
- 4. Nack Negative acknowledge message

Image formats

MSEX supports three image formats for thumbnail and video stream frames;

- RGB8 a raw array of 8-byte RGB triples (this is not BMP). In MSEX 1.0 the byte order was BGR, but from MSEX 1.1 the byte order is RGB.
- PNG the well known file format.
- JPEG the well known file format (which does **not** include EXIF).

10.1 Header definitions

10.1.1 The MSEX header

The MSEX layer provides a standard, single, header used at the start of all MSEX packets:

```
struct CITP_MSEX_Header
{
```

```
CITP_Header CITPHeader; // CITP header. CITP ContentType is "MSEX".

uint8 VersionMajor; // See below.

uint8 VersionMinor; // See below.

uint32 ContentType; // Cookie defining which MSEX message it is.

};
```

The ContentType cookie identifies the specific MSEX message type (e.g. "GETh" for Get Element Thumbnail etc.). If an implementation receives a message with an unrecognised cookie it must silently discard the message and not treat this as an error condition. This is to allow the specification to continue to evolve over time.

10.2 Message definitions: Communication establishment

10.2.1 MSEX / CInf - Client Information message

The Client Information message advises the media server of which versions of MSEX are supported by the client. This message is mandatory and must be sent by the client to the media server immediately after establishing a connection. The media server will examine the list of supported versions and establish the Highest Common MSEX Version defined above.

Note: The format of this message up to FutureMessageData cannot be changed in future versions of MSEX, since the client does not yet know which versions the media server will understand. Future versions can be defined however, but they must preserve the format of the previous version and only insert new fields immediately before the FutureMessageData field.

10.2.2 MSEX / SInf - Server Information message

The Server Information message provides the receiver with product and layer information. This message is mandatory. If the media server supports MSEX 1.0 or 1.1, it should send the v1.0 SInf message immediately after accepting an incoming connection from a lighting console or visualiser. If the media server supports MSEX 1.2 or later, it must send a SInf message in response to a MSEX/CInf message received from the connected client, and the format of that SInf message must match the Highest Common MSEX Version.

```
struct CITP_MSEX_1.0_SInf
    CITP MSEX Header CITPMSEXHeader;
                                                  // CITP MSEX header, MSEX ContentType
                                                      is "SInf". Version is set to 1.0.
                        ProductName[];
                                                  // Display name of the product.
                        ProductVersionMajor; // Major version number of the product.
ProductVersionMinor; // Minor version number of the product.
    uint8
    uint8
                                                  // Number of following layer information blocks.
    uint8
                        LaverCount:
    struct LayerInformation
    {
                       DMXSource[];
        ucs1
                                                // DMX-source connection string. See DMX
                                                     Connection Strings in Definitions.
    };
};
```

A MSEX 1.2 or later version of the MSEX/SInf message is sent in response to a MSEX/CInf Client Information message received from the lighting console or visualiser. The MSEX version used for this message is the Highest Common MSEX Version (described in under MSEX Versions, above).

```
CITP_MSEX_1.2_SInf
    CITP_MSEX_Header CITPMSEXHeader;
                                                    // CITP MSEX header. MSEX ContentType is "SInf".
                                                       Version is at least 1.2 and is the highest common
                                                       version supported by both server and client.
    ucs1
                       UUID[36];
                                                    // A standard 36 character UUID that uniquely
                                                       identifies this media server (see below).
    ucs2
                       ProductName[]:
                                                    // Display name of the product.
                       ProductVersionMajor;
ProductVersionMinor;
                                                    // Major version number of the product.
    uint8
    uint8
                                                   // Minor version number of the product.
    uint8
                       ProductVersionBugfix;
                                                    // Bugfix version number of the product.
```

```
SupportedMSEXVersionsCount; // Number of following MSEX version pairs.
   uint8
                      SupportedMSEXVersions[]; // Each 2 byte value is MSB = major MSEX version,
   uint16
                                                    LSB = minor MSEX version (see below)
   uint16
                      SupportedLibraryTypes;
                                                 // Bit-encoded flagword that identifies which library
                                                    types are provided by the media server (e.g. this
                                                    would be 1 for Media, 2 for Effects, 4 for Cues etc.).
                      ThumbnailFormatsCount;
                                                 // Number of following thumbnail format cookies
   uint8
                      ThumbnailFormats[];
   uint32
                                                // Must include "RGB8", but can also include "JPEG" and
                                                     "PNG " (see below)
                                                // Number of following stream format cookies
   uint8
                      StreamFormatsCount;
                     StreamFormats[];
                                                 // Must include "RGB8", but can also include "JPEG" and
   uint32
                                                     "PNG " (see below)
                                                 // Number of following layer information blocks.
   uint8
                      LayerCount;
   struct LayerInformation
                      DMXSource[];
                                                 // DMX-source connection string. See DMX
       ucs1
                                                    Connection Strings in Definitions.
}:
```

SupportedMSEXVersions: Media Servers that support a specific version of MSEX are not required to support all earlier versions, so this identifies which specific versions are provided.

Format arrays: the order that formats are presented in the ThumbnailFormats and StreamFormats arrays can indicate the Media Server's format preference, the first being the best and the last being the least convenient. Only the "PNG" format can support transparency and it is recommended that all implementations support this format.

10.2.3 MSEX / Nack Negative Acknowledge message

The Negative Acknowledge message is sent in response to any unsupported or unrecognised message received by the Media Server. As with all response messages, the InResponseTo field of the CITP_Header should be set to the same value as the RequestIndex in the corresponding request message. The ReceivedContentType cookie is a copy of the ContentType field in the CITP_MSEX_Header of the corresponding request message. This message is mandatory for MSEX 1.2 and later.

10.3 Message definitions: Layer information

10.3.1 MSEX / LSta - Layer Status message

The LayerStatus message is sent at a regular interval (suggestion: 4 times / second) to provide the receiver with live status information. This message is mandatory.

```
struct CITP_MSEX_1.0_LSta
   CITP_MSEX_Header CITPMSEXHeader;
                                            // CITP MSEX header. MSEX ContentType
                                               is "LSta" and version is 1.0.
                                            // Number of following layer information
   uint8
                     LayerCount;
                                               blocks.
   struct LayerStatus
                                          // 0-based layer number, corresponding to
       uint8
                     LayerNumber;
                                               the layers reported in the SInf message.
                     PhysicalOutput;
                                           // Current physical video output index,
       uint8
                                               0-based.
                     MediaLibraryNumber;
                                           // Current media library number.
       uint8
                     MediaNumber;
                                           // Current media number.
       uint8
                                           // Current media name.
       ucs2
                     MediaName[];
```

```
// Current media position (in frames).
        uint32
                      MediaPosition:
        uint32
                      MediaLength;
                                             // Current media length (in frames).
                                             // Current media resolution in frames per
        uint8
                      MediaFPS;
                                                second.
                                              // Current layer status flags
        uint32
                      LayerStatusFlags;
                                              //
                                                    0x0001 MediaPlaying
    }[];
};
struct CITP_MSEX_1.2_LSta
    CITP MSEX Header CITPMSEXHeader;
                                              // CITP MSEX header. MSEX ContentType
                                                 is "LSta" and version is 1.2.
                                              // Number of following layer information
    uint8
                      LayerCount;
                                                 blocks.
    struct LayerStatus
                                              \ensuremath{//} 0-based layer number, corresponding to
        uint8
                      LaverNumber:
                                                 the layers reported in the SInf message.
                                             // Current physical video output index,
        uint8
                     PhysicalOutput;
                                                 0-based.
                                             // Library content type.
        uint8
                      MediaLibraryType;
       MSEXLibraryId MediaLibraryId;
                                            // Current media library ID. (defined later in
                                                 this specification)
                                             // Current media number.
        uint8
                      MediaNumber;
        ucs2
                     MediaName[];
                                             // Current media name.
        uint32
                      MediaPosition;
                                             // Current media position (in frames).
        uint32
                      MediaLength;
                                             // Current media length (in frames).
        uint8
                      MediaFPS;
                                             // Current media resolution in frames per
                                                 second.
                                              // Current layer status flags
        uint32
                     LayerStatusFlags;
                                                      0x0001 MediaPlaying
                                              //
                                                      0x0002 MediaPlaybackReverse
                                              //
                                                      0x0004 MediaPlaybackLooping
                                              //
                                                      0x0008 MediaPlaybackBouncing
                                              //
                                                      0x0010 MediaPlaybackRandom
                                              11
                                                      0x0020 MediaPaused
    }[];
}:
```

10.4 Message definitions: Element libraries and element information

In MSEX 1.0, there is a finite set of at most 256 libraries, each containing a finite set of at most 256 elements. This is designed to match the common media server layout of 2 dmx channels identifying the library and item respectively.

In MSEX 1.1 however, there is a finite set of at most 3 library levels with at most 256 elements each. Libraries are identified using a library identifier, a 4-byte integer divided into four 1-byte fields. When it's Level byte is set to 0, it is specifying the builtin root level, the parent of all first level libraries.

MSEX 1.0 and 1.1 suffer from a limitation imposed by using a uint8 to represent the LibraryCount and ElementCount values. MSEX 1.2 has removed this limitation by using a uint16 for these numbers, thus allowing library/element counts of up to the prescribed maximum of 256 to be reported.

Beginning with MSEX 1.2, element and library numbers are explicitly defined as being 0-based contiguous index values. E.g. if an element library is reported as containing 10 elements, those element numbers will be 0 thru 9. Prior to MSEX 1.2 the intention was the same, but the specification had been unclear: some implementations of MSEX 1.0 and 1.1 do not honor this pattern and allow for non-continuous library and element identifiers/numbers.

Level1, Level2 and Level3 above are 0-based contiguous indexes for MSEX 1.2.

An attempt to visualize by example the most traditional structure, two levels:

```
/Root Folder (abstract) ID{0,0,0,0}
    /Images ID{1,0,0,0}
    /Primo.gif ID{2,0,0,0}
    /Secundo.gif ID{2,0,1,0}
    /Tertio.gif ID{2,0,2,0}
/Movies ID{1,1,0,0}
```

```
/One.mpg ID{2,1,0,0}
/Two.mpg ID{2,1,1,0}
/Three.avi ID{2,1,2,0}
/Empty folder ID{1,2,0,0}
/Empty folder ID{1,3,0,0}
/More Movies ID{1,4,0,0}
/Test.mpg ID{2,4,0,0}
/Test2.avi ID{2,4,1,0}
```

There are currently eight recognized elements types (a library can only contain elements of one type) and when information about elements is requested, different kinds of Element Information messages (Media, Effect or Generic) are returned:

- 1. Media (images & video)
- 2. Effects
- 3. Cues
- 4. Crossfades
- 5. Masks
- 6. Blend presets
- 7. Effect presets
- 8. Image presets
- 9. 3D meshes

Change Detection

From MSEX 1.2, SerialNumber fields are included in all Element Library Information and Element Information messages. When a Media Server updates an item, that item's SerialNumber is incremented along with the SerialNumber of all parent nodes. E.g. in the above example, if Test2.avi is changed to some different media, the corresponding Media Element Information returned for the new item will have it's SerialNumber incremented, as will the SerialNumber for /More Movies. The Media Server should maintain SerialNumber values between sessions, so that previously connected clients can revalidate their cached information when they re-connect with the Media Server.

DMX Ranges

These value pairs identify the range of values that need to be sent over the corresponding DMX channel in order to select the relevant library or element. If a library contains the maximum 256 elements or sub-libraries, then each element will contain (0,0), (1,1), (2,2) etc. Some Media Servers may choose to distribute fewer elements over the available value range to make selection via an encoder wheel or fader easier. E.g. if a Media Server's media library contains only 10 subfolders, these might be assigned DMX ranges of (0,25), (26,50), (51,75) etc. which would evenly distribute the 10 folders across the full range.

10.4.1 MSEX / GELI - Get Element Library Information message

The GetElementLibraryInfo message is sent to a media server in order to request information about an element library, or all available element libraries.

```
struct CITP MSEX 1.0 GELI
   CITP_MSEX_Header CITPMSEXHeader;
                                               // CITP MSEX header. MSEX ContentType
                                                  is "GELI" and version is 1.0.
                                               // Content type requested.
   uint8
                      LibraryType;
   uint8
                      LibraryCount;
                                               // Number of libraries requested, set to
                                                   0 when requesting all available.
                                               // Requested library numbers, none if
                     LibraryNumbers[];
   uint8
                                                   LibraryCount is 0.
};
struct CITP MSEX 1.1 GELI
                                               // CITP MSEX header. MSEX ContentType
   CITP_MSEX_Header CITPMSEXHeader;
                                                  is "GELI" and version is 1.1.
                                                // Content type requested.
   uint8
                      LibraryType;
   MSEXLibraryId
                      LibraryParentId;
                                               // Parent library id.
                                               // Number of libraries requested, set to
   uint8
                     LibrarvCount:
                                                   0 when requesting all available.
                      LibraryNumbers[];
                                               // Requested library numbers, none if
   uint8
                                                   LibraryCount is 0.
};
```

The MSEX 1.2 version of this message uses a uint16 for LibraryCount to avoid the limitation described in "Message Definitions: Element libraries and element information":

Example 1: two DMX channel media selection media server. A GELI message with LibraryParentId set to {0, 0, 0, 0} is sent to retrieve all libraries on the folder selection channel. This generates a response with an ELIn message with at most 256 items with LibraryId values of {1, 0-255, 0, 0}.

Example 2: three DMX channel media selection media server. First the procedure in Example 1 is executed to collect all Level 1 libraries (none of these will contain any elements, but up to 256 sub libraries). For each N of these (up to 256) libraries, an additional GELI message is sent with the LibraryParentId set to {1, N, 0, 0}. This will trigger a response with an ELin message with at mosts 256 items with LibraryId values of {2, N, 0-255, 0}.

Note: Prior to MSEX 1.2 there is a limitation caused by the use of a uint8 to represent the library/element count, in which case the above examples can report at most 255 libraries and 255 elements within a library. See "Message definitions: Element libraries and element information", above

10.4.2 MSEX / ELIn - Element Library Information message

The ElementLibraryInfo message is sent in response to the GetElementLibraryInfo message. It should contain individual element library information for the *entire contents* of the requested element library.

```
struct CITP_MSEX_1.0_ELIn
{
   CITP_MSEX_Header CITPMSEXHeader;
                                             // CITP MSEX header. MSEX ContentType
                                                is "ELIn" and version is 1.0.
                     LibraryType;
                                              // Content type requested.
   uint8
                    LibraryCount;
                                             // Number of following element library
   uint8
                                                 information blocks.
   struct ElementLibraryInformation
                                              // 0-based library number.
       uint8
                     Number:
                  DMXRangeMin;
DMXRangeMax;
                                              // DMX range start value.
       uint8
       uint8
                                             // DMX range end value.
       ucs2
                                             // Library name.
                    Name[];
                ElementCount;
                                             // Number of elements in the library.
       uint8
   }[];
};
struct CITP_MSEX_1.1_ELIn
                                            // CITP MSEX header. MSEX ContentType
   CITP_MSEX_Header CITPMSEXHeader;
                                                 is "ELIn" and version is 1.1.
                                             // Content type requested.
                    LibraryType;
                                             // Number of following element library
   uint8
                     LibraryCount;
                                                 information blocks.
   struct ElementLibraryInformation
                                             // Library id.
       MSEXLibraryId Id;
       // DMX range start value.
                                             // DMX range end value.
// Library name.
       uint8
                    DMXRangeMax;
                    Name[];
       ucs2
                                            // Number of sub libraries
       uint8
                    LibraryCount;
                                                 in the library.
       uint8
                    ElementCount;
                                             // Number of elements in the library.
   }[];
```

The MSEX 1.2 version of this message uses a uint16 for LibraryCount & ElementCount to avoid the limitation described in "Message Definitions: Element libraries and element information":

```
struct ElementLibraryInformation
    {
                                               // Library id.
       MSEXLibraryId Id;
       uint32
                     SerialNumber;
                                              // See below
       uint8
                     DMXRangeMin;
                                              // DMX range start value.
                                              // DMX range end value.
       uint8
                     DMXRangeMax;
       ucs2
                     Name[];
                                              // Library name.
       uint16
                     LibraryCount;
                                              // Number of sub libraries in the library (0-256).
       uint16
                      ElementCount;
                                               // Number of elements in the library (0-256).
   }[];
};
```

SerialNumber: this field is used to detect changes to an element library. See Change Detection above.

10.4.3 MSEX / ELUp - Element Library Updated message

The ElementLibraryUpdated message is sent by a media server to notify a console or visualizer about updated media library contents.

```
struct CITP MSEX 1.0 ELUp
   CITP MSEX Header CITPMSEXHeader;
                                               // CITP MSEX header. MSEX ContentType
                                                   is "ELUp" and version is 1.0.
                                               // Content type of updated library.
   uint8
                     LibraryType;
                   LibraryNumber;
   uint8
                                               // Library that has been updated.
                     UpdateFlags;
                                                // Additional information flags.
                                                //
                                                        0x01 Existing elements have been
                                                               updated
                                                        0x02
                                                             Elements have been added or
                                                              removed
                                                // 0x04 Sub libraries have been updated
                                                // 0x08 Sub libraries have been added or removed
};
struct CITP_MSEX_1.1_ELUp
   CITP_MSEX_Header CITPMSEXHeader;
                                               // CITP MSEX header. MSEX ContentType
                                                  is "ELUp" and version is 1.1.
   uint8
MSEXLibraryId LibraryId;
UpdateFlags;
                                               // Content type of updated library.
                    LibraryType;
                                               // Library that has been updated.
                                               // Additional information flags.
                                                //
                                                        0x01 Existing elements have been
                                                               updated
                                                      0x02 Elements have been added or
                                                //
                                                               removed
                                                // 0x04 Sub libraries have been updated
                                                // 0x08 Sub libraries have been added or removed
};
struct CITP_MSEX_1.2_ELUp
   CITP_MSEX_Header CITPMSEXHeader;
                                               // CITP MSEX header. MSEX ContentType
                                                  is "ELUp" and version is 1.2.
                                               // Content type of updated library.
                      LibraryType;
   MSEXLibraryId
                                               // Library that has been updated.
                     LibrarvId:
   uint8
                      UpdateFlags;
                                               // Additional information flags.
                                                // 0x01 Existing elements have been updated
                                                // 0x02 Elements have been added or removed
                                                // 0x04 Sub libraries have been updated
                                                // 0x08 Sub libraries have been added or removed
                                                // 0x10 All elements have been affected
                                                        (ignore AffectedElements)
                                                // 0x20 All sub libraries have been affected
                                                       (ignore AffectedLibraries)
   AffectedItems
                      AffectedElements;
                                               // Which elements have been affected
                      AffectedLibraries;
                                               // Which sub-libraries have been affected
   AffectedItems
};
```

The MSEX 1.2 (and later) version of ELUp contains extra detail to identify which elements and/or sublibraries have been changed.

E.g. the following test will be true if the element or library indexed by ItemIndex has changed:

10.4.4 MSEX / GEIn - Get Element Information message

The GetElementInformation message is sent by a console or visualizer to a media server in order to request information about individual elements.

```
struct CITP_MSEX_1.0_GEIn
                                              // CITP MSEX header. MSEX ContentType
    CITP_MSEX_Header CITPMSEXHeader;
                                            is "GEIn" and version is "Content type requested.

// Library for which
                                                    is "GEIn" and version is 1.0.
    uint8
                      LibraryType;
                                                // Library for which to retrieve element info.
    uint8
                      LibraryNumber;
                      ElementCount;
                                                // Number of elements for which information
    uint8
                                                    is requested, set to 0 when requesting
                                                    all available.
                     ElementNumbers[];
                                                // Numbers of the elements for which
    uint8
                                                    information is requested.
};
struct CITP MSEX 1.1 GEIn
    CITP_MSEX_Header CITPMSEXHeader;
                                                // CITP MSEX header. MSEX ContentType
                                                    is "GEIn" and version is 1.1.
    uint8
                      LibraryType;
                                                 // Content type requested.
   MSEXLibraryId
uint8
                      LibraryId;
                                                 // Library for which to retrieve elements
                     ElementCount;
                                                // Number of elements for which information
                                                    is requested, set to 0 when requesting
                                                    all available.
    uint8
                                               // Numbers of the elements for which
                       ElementNumbers[];
                                                    information is requested.
};
```

The MSEX 1.2 version of this message uses a uint16 for ElementCount to avoid the limitation described in "Message Definitions: Element libraries and element information":

10.4.5 MSEX / MEIn - Media Element Information message

The MediaElementInformation message is sent in response to the GetElementInformation message for element type 1. It should contain individual media element information for *all* elements requested.

```
struct CITP_MSEX_1.0_MEIn
    CITP_MSEX_Header CITPMSEXHeader; // CITP MSEX header. MSEX ContentType
                                                          is "MEIn" and version is 1.0.
                         LibraryNumber;
                                                      // Library containing the media elements.
    uint8
                         ElementCount;
    uint8
                                                      // Number of following (media) information
                                                          blocks.
    struct MediaInformation
                                           // U-Dasce
// DMX range start value
// DMX range end value.
// Media name.
// Media version in sec
                                                      // 0-based number of the media.
        uint8
                        Number:
                                                     // DMX range start value.
        uint8
                        DMXRangeMin;
                      DMXRangeMax; // DMX range end value.

MediaName[]; // Media name.

MediaVersionTimestamp; // Media version in seconds since
        uint8
         ucs2
        uint64
                                                          1st January 1970.
                   MediaWidth;
MediaHeight;
                                                      // Media width.
        uint16
                                                // Media height.
// Media length
         uint16
                        MediaLength;
        uint32
                                                      // Media length (in frames).
                                                      // Media resolution (in frames per second).
         uint8
                        MediaFPS;
    }[];
};
struct CITP_MSEX_1.1_MEIn
    CITP MSEX Header CITPMSEXHeader;
                                                      // CITP MSEX header. MSEX ContentType
```

```
is "MEIn" and version is 1.1.
                                                   // Library containing the media elements.
    MSEXLibraryId
                       LibraryId;
    uint8
                        ElementCount;
                                                   // Number of following (media) information
                                                      blocks.
    struct MediaInformation
        uint8
                       Number:
                                                   // 0-based number of the media.
                                                   // DMX range start value.
                      DMXRangeMin;
        uint8
                    DMXRangeMin;
DMXRangeMax;
MediaName[];
                                                  // DMX range end value.
        uint8
                       MediaName[]; // Media name.
MediaVersionTimestamp; // Media version in seconds since
        ucs2
        uint64
                                                      1st January 1970.
                    MediaWidth;
MediaHeight;
MediaLength;
                                                   // Media width.
        uint16
                                                  // Media height.
        uint16
                                                  // Media length (in frames).
        uint32
                       MediaFPS;
        uint8
                                                   // Media resolution (in frames per second).
    }[];
};
```

The MSEX 1.2 version of this message uses a uint16 for ElementCount to avoid the limitation described in "Message Definitions: Element libraries and element information":

```
struct CITP_MSEX_1.2_MEIn
    CITP MSEX Header CITPMSEXHeader;
                                                      // CITP MSEX header. MSEX ContentType
                                                           is "MEIn" and version is 1.1.
    MSEXLibraryId
                                                       // Library containing the media elements.
                         LibraryId;
                         ElementCount;
    uint16
                                                      // Number of following (media) information
                                                          blocks.
    struct MediaInformation
        uint8
                                                       // 0-based contiguous index of the media.
                         Number:
                       SerialNumber;
        uint32 SerialNumber; // See below
uint8 DMXRangeMin; // DMX range start value.
uint8 DMXRangeMax; // DMX range end value.
ucs2 MediaName[]; // Media name.
uint64 MediaVersionTimestamp; // Media version in seconds since
                                                          1st January 1970.
        // Media width.
                                                      // Media height.
                                                      // Media length (in frames).
        uint32
                        MediaLength;
         uint8
                         MediaFPS:
                                                       // Media resolution (in frames per second).
    }[];
```

SerialNumber: this field is used to detect changes to an element within a library. See Change Detection above.

10.4.6 MSEX / EEIn - Effect Element Information message

The EffectElementInformation message is sent in response to the GetElementInformation message for element type 2. It contains individual effect element information for *all* elements requested.

```
struct CITP MSEX 1.0 EEIn
   CITP MSEX Header CITPMSEXHeader;
                                              // CITP MSEX header. MSEX ContentType
                                                 is "EEIn" and version is 1.0.
   uint8
                     LibraryNumber;
                                              // Library containing the effect elements.
                                              // Number of following (effect) information
   uint8
                     ElementCount;
                                                 blocks.
   struct EffectInformation
                                             // 0-based number of the effect.
       uint8
                     ElementNumber;
                                             // DMX range start value.
       uint8
                    DMXRangeMin;
                    DMXRangeMax;
EffectName[];
       uint8
                                              // DMX range end value.
                                              // Effect name.
       ucs2
                    EffectParameterCount; // Number of following effect
       uint8
                                                 parameter names.
                    EffectParameterNames[][]; // List of effect parameter names.
       ucs2
   }[];
struct CITP MSEX 1.1 EEIn
   CITP_MSEX_Header CITPMSEXHeader;
                                             // CITP MSEX header. MSEX ContentType
                                                 is "EEIn" and version is 1.1.
                                             // Library containing the effect elements.
   MSEXLibraryId
                    LibraryId;
                                          // Library containing one city information
   uint8
                     ElementCount;
                                                 blocks.
   struct EffectInformation
```

```
// 0-based number of the effect.
                 ElementNumber;
      uint8
                DMXRangeMin;
DMXRangeMax;
                                      // DMX range start value.
      uint8
                                     // DMX range end value.
      uint8
                 ucs2
      uint8
                                        parameter names.
                 EffectParameterNames[][]; // List of effect parameter names.
      ucs2
   }[];
};
```

The MSEX 1.2 version of this message uses a uint16 for ElementCount to avoid the limitation described in "Message Definitions: Element libraries and element information":

```
struct CITP_MSEX_1.2_EEIn
   CITP_MSEX_Header CITPMSEXHeader; // CITP MSEX header. MSEX ContentType
                                                      is "EEIn" and version is 1.1.
                                                  // Library containing the effect elements.
    MSEXLibraryId
                       LibraryId;
                       ElementCount;
                                                  // Number of following (effect) information
    uint16
                                                      blocks.
    struct EffectInformation
                                               // 0-based contiguous index of the effect.
// See below
// DMX range start value.
                     ElementNumber;
        uint8
                       SerialNumber;
        uint32
        uint8
                      DMXRangeMin;
                                                 // DMX range end value.
                     DMXRangeMax;
EffectName[];
        uint8
                      EffectName[]; // Effect name.
EffectParameterCount; // Number of following effect
        ucs2
        uint8
                                                      parameter names.
                      EffectParameterNames[][]; // List of effect parameter names.
        ucs2
    }[];
```

SerialNumber: this field is used to detect changes to an element within a library. See Change Detection above.

10.4.7 MSEX / GLEI - Generic Element Information message

The GenericElementInformation message is sent in response to the GetElementInformation message for element types 3 through 8. It contains individual element information for *all* elements requested.

```
struct CITP_MSEX_1.1_GLEI
                                                   // CITP MSEX header. MSEX ContentType
    CITP_MSEX_Header CITPMSEXHeader;
                                                         is "GLEI" and version is 1.1.
    MSEXLibraryId
                                                     // Library containing the elements.
                       LibrarvId:
                         ElementCount;
    uint8
                                                     // Number of following information
                                                         blocks.
    struct GenericInformation
                                              // 0-based number of the element.
// DMX range start value.
// DMX range end ---
                        ElementNumber;
        uint8
                     DMXRangeMin;
DMXRangeMax;
        uint8
                                                    // DMX range end value.
// Element name.
// Element version in
        uint8
        ucs2 Name[];
uint64 VersionTimestamp;
                       Name[];
        ucs2
                                                     seconds since 1st January 1970.
    }[];
```

Note: The MSEX 1.1 version of this message lacks a field indicating which library type the contained information belongs to (which is not necessary with the MEIn and EEIn messages since each is for a particular library type). The MSEX 1.2 version of this message defined below corrects this problem, as well as ElementCount limitation described in "Message Definitions: Element libraries and element information":

```
struct CITP_MSEX_1.2_GLEI
   CITP_MSEX_Header CITPMSEXHeader;
                                            // CITP MSEX header. MSEX ContentType
                                                 is "GLEI" and version is 1.1.
                                              // Library content type.
   uint8
                     LibraryType;
   MSEXLibraryId
                     LibraryId;
                                              // Library containing the elements.
                                             // Number of following information
   uint16
                    ElementCount:
                                                 blocks.
   struct GenericInformation
                                          // 0-based contiguous index of the element.
       uint8
                    ElementNumber;
                 SerialNum.
DMXRangeMin;
                     SerialNumber;
       uint32
                                              // See below
                                             // DMX range start value.
       uint8
                   DMXRangeMax;
       uint8
                                             // DMX range end value.
       ucs2
                                              // Element name.
                     Name[];
       uint64
                    VersionTimestamp;
                                             // Element version in
```

```
}[];
};
```

SerialNumber: this field is used to detect changes to an element within a library. See Change Detection above.

10.5 Message definitions: Thumbnail information

10.5.1 MSEX / GELT - Get Element Library Thumbnail message

The GetElementLibraryThumbnail message is sent to a media server in order to retrieve a thumbnail of an element library, or of all available element libraries.

```
struct CITP_MSEX_1.0_GELT
   CITP_MSEX_Header
                      CITPMSEXHeader:
                                              // CITP MSEX header. MSEX ContentType
                                                 is "GELT" and version is 1.0.
                                              // Format of the thumbnail.
   uint32
                       ThumbnailFormat:
                                                 Can be "RGB8" or "JPEG" (or "PNG" for MSEX 1.2 and up).
   uint16
                       ThumbnailWidth;
                                              // Preferred thumbnail image width.
                                              // Preferred thumbnail image height.
   uint16
                       ThumbnailHeight;
   uint8
                       ThumbnailFlags
                                              // Additional information flags.
                                              //
                                                      0x01
                                                            Preserve aspect ratio
                                                of image (use width and height as maximum)
                                              // 1 for Media, 2 for Effects.
   11 i n + 8
                      LibraryType;
   uint8
                      LibraryCount;
                                              // Number of libraries requested, set to 0
                                                 when requesting all available.
   uint8
                      LibraryNumbers[];
                                              \ensuremath{//} Numbers of the libraries requested, not present
                                                if LibraryCount is 0.
};
struct CITP_MSEX_1.1_GELT
   CITP MSEX Header CITPMSEXHeader;
                                              // CITP MSEX header. MSEX ContentType
                                                 is "GELT" and version is 1.1.
   uint32
                      ThumbnailFormat;
                                              // Format of the thumbnail.
                                                 Can be "RGB8" or "JPEG" (or "PNG" for MSEX 1.2 and up).
                                              // Preferred thumbnail image width.
   uin+16
                      ThumbnailWidth:
                                             // Additional information flags.
   uint16
                       ThumbnailHeight;
                                              // Preferred thumbnail image height.
                       ThumbnailFlags
                                                            Preserve aspect ratio
                                                of image (use width and height as maximum)
   uint8
                       LibraryType;
                                              // 1 for Media, 2 for Effects.
                                              // Number of libraries requested, set to 0
   uint8
                      LibraryCount;
                                                 when requesting all available.
   MSEXLibraryId
                      LibraryIds[];
                                              // Ids of the libraries requested, not present if
                                                 LibraryCount is 0.
};
```

The MSEX 1.2 version of this message uses a uint16 for LibraryCount to avoid the limitation described in "Message Definitions: Element libraries and element information":

```
struct CITP_MSEX_1.2_GELT
{
   CITP MSEX Header CITPMSEXHeader;
                                             // CITP MSEX header. MSEX ContentType
                                                is "GELT" and version is 1.2.
                                             // Format of the thumbnail.
   uint32
                      ThumbnailFormat;
                                                Can be "RGB8" or "JPEG" (or "PNG" for MSEX 1.2 and up).
                                             // Preferred thumbnail image width.
   uint16
                      ThumbnailWidth:
                                             // Preferred thumbnail image height.
   11 in+16
                      ThumbnailHeight:
                                             // Additional information flags.
   uint8
                      ThumbnailFlags
                                             //
                                                     0x01
                                                          Preserve aspect ratio
                                                of image (use width and height as maximum)
                                            // 1 for Media, 2 for Effects.
   uint8
                     LibraryType;
                      LibraryCount;
                                             // Number of libraries requested, set to 0
   uint16
                                                when requesting all available.
   MSEXLibraryId
                     LibraryIds[];
                                             // Ids of the libraries requested, not present if
                                                LibraryCount is 0.
};
```

10.5.2 MSEX / ELTh - Element Library Thumbnail message

The ElementLibraryThumbnail message is sent in response to the GetElementLibraryThumbnail message.

```
// 1 for Media, 2 for Effects.
    uint8
                        LibraryType:
    uint8
                        LibraryNumber;
                                                // Number of the library that
                                                          the thumbnail belongs to.
                                                // Format of the thumbnail.
Can be "RGB8" or "JPEG" (or "PNG " for MSEX 1.2 and up).
                        ThumbnailFormat:
    uint32
    uint16
                        ThumbnailWidth;
                                                // Thumbnail width.
                                                // Thumbnail height.
// Size of the thumbnail buffer.
    uint16
                        ThumbnailHeight:
    uint16
                        ThumbnailBufferSize;
                        ThumbnailBuffer[];
                                                // Thumbnail image buffer.
    uint8
};
struct CITP_MSEX_1.1_ELTh
    CITP MSEX Header CITPMSEXHeader;
                                                // CITP MSEX header. MSEX ContentType
                                                   is "ELTh" and version is 1.1.
                                                // 1 for Media, 2 for Effects.
    uint8
                        LibraryType;
                        LibraryId;
    MSEXLibraryId
                                                // Id of the library that the thumbnail
                                                   belongs to.
                                                // Format of the thumbnail.
    uint32
                        ThumbnailFormat:
                                                   Can be "RGB8" or "JPEG" (or "PNG" for MSEX 1.2 and up).
                                                // Thumbnail width.
    uint16
                        ThumbnailWidth:
                                                // Thumbnail height.
    uint16
                        ThumbnailHeight;
    uint16
                        ThumbnailBufferSize; // Size of the thumbnail buffer.
                        ThumbnailBuffer[];
    uint8
                                                // Thumbnail image buffer.
```

10.5.3 MSEX / GETh - Get Element Thumbnail message

The GetElementThumbnail message is sent to a media server in order to retrieve a thumbnail of one or many library elements..

```
struct CITP_MSEX_1.0_GETh
    CITP MSEX Header CITPMSEXHeader;
                                              // CITP MSEX header. MSEX ContentType
                                                 is "GETh" and version is 1.0.
                       ThumbnailFormat;
                                              // Format of the thumbnail.
    uint32
                                                 Can be "RGB8" or "JPEG" (or "PNG" for MSEX 1.2 and up).
                                              // Preferred thumbnail image width.
    uint16
                       ThumbnailWidth:
    uint16
                       ThumbnailHeight;
                                              // Preferred thumbnail image height.
    uint8
                       ThumbnailFlags
                                              // Additional information flags.
                                              // 0x01
                                                       Preserve aspect ratio of image
                                                        (use width and height as maximum)
    uint8
                                              // 1 for Media, 2 for Effects.
                       LibraryType;
                                              // Number of the media's library.
    uint8
                       LibraryNumber;
    uint8
                       ElementCount;
                                              // Number of medias for which information
                                                 is requested, set to 0 when requesting
                                                 all available.
    uint8
                       ElementNumbers[];
                                              // The numbers of the requested elements.
                                                 Not present if ElementCount is 0.
};
struct CITP_MSEX_1.1_GETh
    CITP MSEX Header CITPMSEXHeader;
                                              // CITP MSEX header. MSEX ContentType
                                                 is "GETh" and version is 1.1.
    uint32
                       ThumbnailFormat;
                                              // Format of the thumbnail.
                                                 Can be "RGB8" or "JPEG" (or "PNG" for MSEX 1.2 and up).
                                              // Preferred thumbnail image width.
    uint16
                       ThumbnailWidth:
    uint16
                       ThumbnailHeight;
                                              // Preferred thumbnail image height.
                                              // Additional information flags.
    uint8
                       ThumbnailFlags
                                              // 0x01
                                                       Preserve aspect ratio of image
                                                        (use width and height as maximum)
    uint8
                       LibraryType;
                                              // 1 for Media, 2 for Effects.
    MSEXLibraryId
                                              // Id of the media's library.
                       LibraryId;
    uint8
                       ElementCount;
                                              // Number of medias for which information
                                                 is requested, set to 0 when requesting
                                                 all available.
    uint8
                       ElementNumbers[];
                                              // The numbers of the requested elements.
                                                 Not present if ElementCount = 0. For MSEX 1.2 these are
                                                 0-based contiguous index values.
};
```

The MSEX 1.2 version of this message uses a uint16 for ElementCount to avoid the limitation described in "Message Definitions: Element libraries and element information":

```
// Preferred thumbnail image width.
   uint16
                       ThumbnailWidth:
                                              // Preferred thumbnail image height.
   uint16
                       ThumbnailHeight;
                                              // Additional information flags.
   uint8
                       ThumbnailFlags
                                              // 0x01 Preserve aspect ratio of image
                                                         (use width and height as maximum)
   uint8
                                              // 1 for Media, 2 for Effects.
                      LibraryType;
                                              // Id of the media's library.
   MSEXLibraryId
                       LibraryId;
                                              // Number of medias for which information
   uint16
                       ElementCount;
                                                 is requested, set to 0 when requesting
                                                 all available.
   uint8
                       ElementNumbers[];
                                              \ensuremath{//} The numbers of the requested elements.
                                                 Not present if ElementCount = 0. For MSEX 1.2 these are
                                                 0-based contiguous index values.
};
```

10.5.4 MSEX / EThn - Element Thumbnail message

The ElementLibraryThumbnail message is sent in response to the GetElementLibraryThumbnail message.

```
struct CITP MSEX 1.0 EThn
    CITP_MSEX_Header CITPMSEXHeader;
                                             // CITP MSEX header. MSEX ContentType
                                                 is "EThn" and version is 1.0.
                                            // 1 for Media, 2 for Effects.
    uint8
                      LibraryType;
                                            // Number of the element's library.
// Number of the element.
    uint8
                       LibraryNumber;
    uint8
                      ElementNumber;
                      ThumbnailFormat;
                                            // Format of the thumbnail.
    uint32
                                                 Can be "RGB8" or "JPEG" (or "PNG" for MSEX 1.2 and up).
                                         // Thumbnail width.
    uint16
                     ThumbnailWidth;
                     ThumbnailHeight;
                      ThumbnailHeight; // Thumbnail height.
ThumbnailBufferSize; // Size of the thumbnail buffer.
    uint16
    uint16
                                             // Thumbnail image buffer.
    uint8
                      ThumbnailBuffer[];
};
struct CITP_MSEX_1.1_EThn
    CITP_MSEX_Header CITPMSEXHeader;
                                             // CITP MSEX header. MSEX ContentType
                                                 is "EThn" and version is 1.1.
                                              // 1 for Media, 2 for Effects.
    uint8
                       LibraryType;
    MSEXLibraryId
                      LibraryId;
                                             // Id of the element's library.
    uint8
                      ElementNumber;
                                             // Number of the element (For MSEX 1.2 this
                                                is a 0-based contiguous index value).
    uint32
                      ThumbnailFormat;
                                             // Format of the thumbnail.
                                                 Can be "RGB8" or "JPEG" (or "PNG" for MSEX 1.2 and up).
                                             // Thumbnail width.
    uint16
                       ThumbnailWidth;
                                             // Thumbnail height.
    uint16
                       ThumbnailHeight;
                       ThumbnailBufferSize; // Size of the thumbnail buffer.
    uint16
                                              // Thumbnail image buffer.
    uint8
                       ThumbnailBuffer[];
};
```

10.6 Message definitions: Streams

10.6.1 MSEX / GVSr - GetVideoSources

The GetVideoSources message is sent to a media server in order to receive all available video source feeds.

10.6.2 MSEX / VSrc - Video Sources

The VideoSources message is sent in response to a GetVideoSources message. The PhysicalOutput and LayerNumber fields can be used for automatic connection to outputs and individual layers (for instance the video of output 1 would have PhysicalOutput = 0 and LayerNumber = 0xFF).

```
ucs2
                   SourceName[];
                                           // Display name of the source (ie "Output 1",
                                              "Layer 2", "Camera 1" etc).
    uint8
                   PhysicalOutput;
                                           // If applicable, 0-based index designating
                                              the physical video output index.
                                              Otherwise OxFF.
                                           // If applicable, 0-based layer number,
    uint8
                   LayerNumber;
                                              corresponding to the layers reported in
                                              the SInf message. Otherwise OxFF.
                                          // Information flags.
    uint16
                   Flags;
                                          //
                                                  0x0001 Without effects
                                          // Full width.
    uint16
                   Width;
                                          // Full height.
    uint16
                   Height;
};
```

10.6.3 MSEX / RqSt - Request Stream message

The RequestStream message is sent by a console or visualizer to a media server in order to create a time limited subscription of a video source. The media server will not provide multiple resolutions and frame rates of a single source, but it may provide a feed for each requested format. If different resolutions are requested by multiple peers, the Media Server should only supply the higher resolution to all peers (any peer should be prepared to downscale). It is up to the peer to regularly request a stream, based on its timeout parameter, if it wishes receive a continuous feed. High values of the timeout field is of course discouraged.

```
struct CITP_MSEX_RqSt
   CITP_MSEX_Header
                      CITPMSEXHeader;
                                              // CITP MSEX header. MSEX ContentType
                                                 is "RqSt".
                                              // Identifier of the source requested.
   uint16
                      SourceIdentifier:
   uint32
                      FrameFormat;
                                             // Requested frame format.
                                                 Can be "RGB8" or "JPEG" (or "PNG" for MSEX 1.2 and up).
   uint16
                      FrameWidth:
                                             // Preferred minimum frame width.
                                             // Preferred minimum frame height.
   uint16
                      FrameHeight;
   uint8
                                             // Preferred minimum frames per second.
   uint8
                      Timeout:
                                             // Timeout in seconds (for instance 5
                                                 seconds, 0 to ask for only one frame).
};
```

10.6.4 MSEX / StFr - Stream Frame message

The StreamFrame message is multicasted regularly from a media server. The resolutions, formats and FPS are determine by the current set of subscribing peers.

```
struct CITP_MSEX_1.0_StFr
{
   CITP_MSEX_Header CITPMSEXHeader;
                                             // The CITP MSEX header. MSEX ContentType
                                               is "StFr".
                                             // Identifier of the frame's source.
   uint16
                      SourceIdentifier:
   uint32
                      FrameFormat;
                                            // Requested frame format.
                                                Can be "RGB8" or "JPEG" (or "PNG" for MSEX 1.2 and up).
   uint16
                      FrameWidth;
                                            // Preferred minimum frame width.
                                            // Preferred minimum frame height.
   uint16
                      FrameHeight;
                      FrameBufferSize;
                                            // Size of the frame image buffer.
   uint16
   uint8
                      FrameBuffer[];
                                             // Frame image buffer.
```

Prior to version 1.1 of MSEX, RGB8 data was transmitted as BGR rather then RGB. As of version 1.1, stream frames are to be transmitted over the multicast channel only (sames as used by PINF) and never over the TCP connection.

```
struct CITP_MSEX_1.2_StFr
   CITP MSEX Header CITPMSEXHeader;
                                             // The CITP MSEX header. MSEX ContentType
                                                is "StFr".
   ucs1
                      MediaServerUUID[36]; // Source media server UUID, see below.
                      SourceIdentifier;
   uint16
                                            // Identifier of the frame's source.
                                             // Requested frame format.
   uint32
                      FrameFormat:
                                                Can be "RGB8" or "JPEG" (or "PNG" for MSEX 1.2 and up).
   uint16
                      FrameWidth;
                                            // Preferred minimum frame width.
                                            // Preferred minimum frame height.
   uint16
                      FrameHeight;
   uint16
                      FrameBufferSize;
                                            // Size of the frame image buffer.
                      FrameBuffer[];
   uint8
                                             // Frame image buffer.
```

As of version 1.2, the source media server UUID was added as a means of distinguishing incoming stream frames from different media servers on the same IP address.